



[EVD PPE DONNING PROCESS]

Staff are required to follow the following check sheet with no deviation from this protocol.

1. Collect all PPE prior to Donning :	Complete	Observation
Tyvek suit (quick seal placed on the zipper) Tyvek Boot Covers Tyvek Apron Safety Glasses Face Shield N95 Mask Exam Gloves Long Cuff Exam Gloves Tape Bottle of Water Disinfectant Wipes	<input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/> <input type="checkbox"/>	Inspect each piece of equipment to ensure the integrity that that no rips or tears are present
2. Document Pre Donning Vitals on all staff involved on the EVD Response Tracking sheet	<input type="checkbox"/>	Sheet attached
3. Remove all Jewelry, Rings, Watches and Necklaces (small stud earrings may be permissible) and place in a med bag for safe keeping.	<input type="checkbox"/>	Check for any objects that may cause a tear in the suit if caught on something
4. Hydrate with Bottled Water	<input type="checkbox"/>	Staff need to drink water as they may be in the suit for extended time
5. Remove Uniform shirt	<input type="checkbox"/>	Shirt Collars catch on the suit when doffing
6. Tuck Pants Into socks or tape pants around ankles	<input type="checkbox"/>	This assists in donning and doffing
7. Tape over any boot zippers	<input type="checkbox"/>	Zippers can catch on covers
8. Remove items from pockets, paramedic scissors and belt buckles	<input type="checkbox"/>	Check for any protrusions that may puncture suit
9. Long haired staff members to tieback hair or use a OR hair net	<input type="checkbox"/>	Check that hair is contained so it does not impede sight
10. Wash hands with approved hand sanitizer	<input type="checkbox"/>	Start off clean
11. Place the Tyvek Suit on	<input type="checkbox"/>	Ensure proper fit, Staff can squat and lunge safely
12. Place Boot Covers on	<input type="checkbox"/>	Place boot covers under suit pants
13. Tape suit pants to boot covers - Do not tape tightly around ankles as this will be a hazard during doffing try taping suit legs and covers together only once around	<input type="checkbox"/>	Confirm dog ears are used on the tape for easy removal
14. Place Tyvek Apron on and secure ties in bow	<input type="checkbox"/>	No knots for easy removal
15. Put on inner exam gloves	<input type="checkbox"/>	No rips
16. Place Long cuff gloves on over suit arms	<input type="checkbox"/>	No rips
17. Tape Long cuff gloves to suit arms as high up as possible. This will assist in doffing the gloves and suit as	<input type="checkbox"/>	Confirm dog ears are used on the tape for



[EVD PPE DONNING PROCESS]

Staff are required to follow the following check sheet with no deviation from this protocol.

one unit.		easy removal if needed
18. N95 mask placed on and self-fit tested	<input type="checkbox"/>	No leaks or air movement during fit test and mask straps are above and below back of head
19. Eye Protection Placed on	<input type="checkbox"/>	Proper fit
20. Face Shield Placed on head (face shield may have to be placed on after the suit hood is up depending on the suit size and make)		Shield should go under hood for good fit but may be used over if needed
21. Place Suit Hood on	<input type="checkbox"/>	Complete coverage of head area
22. Tyvek suit zipped up with neck covered	<input type="checkbox"/>	If neck area not covered appropriately by suit place tape over the exposed area with dog ears on tape
23. Final Inspection – Staff to turn around and be able to lunge, squat and self-hug	<input type="checkbox"/>	Check for tears, rips, skin showing
24. Words of encouragement! (Remind staff to take a zip lock bag with approved disinfectant wipes for mitigation procedures if needed)	<input type="checkbox"/>	Acknowledge the stress staff will feel and remind them that they are now safe